ECS455 Chapter 2

Cellular Systems

2.2 Co-Channel Interference

Dr. Prapun Suksompong prapun.com/ecs455

Office Hours:

BKD 3601-7


Monday 9:20-10:20

Wednesday 9:20-10:20

(Intercell)

Co-Channel Interference

- Frequency reuse → co-channel interference
- Consider only nearby interferers.
 - Power decreases rapidly as the distance increases.
- In a fully equipped hexagonal-shaped cellular system, there are always K = 6 cochannel interfering cells in the first tier.



Three Measures of Signal Quality

- Old (**noise-limited** systems) SNR = $\frac{P_r}{P_{\text{noise}}}$
- Consider both noise & interference SINR = $\frac{P_r}{P_{\text{interference}} + P_{\text{noise}}}$
- The best cellular system design places users that share the same channel at a separation distance (as close as possible) Why where the intercell interference is just below the maximum tolerable level for the required data rate and BER.
- Good cellular system designs are interference-limited, meaning that the interference power is much larger than the noise power.

"Reliable"/"tolerable"?

(Why not as far as possible?)

Co-channel cells, must be spaced **far enough** apart so that interference between users in co-channel cells does not degrade **signal quality** below tolerable levels.

Subjective tests found that people regard an FM signal using a 30 kHz channel bandwidth to be clear if the signal power is at least sixty times higher than the noise/interference power.

[Klemens, 2010, p 54]

$$10\log_{10} 60 = 17.78 \approx 18 \text{ dB}$$

We will soon revisit and use these numbers for some more specific calculations

Review: Simplified Path Loss Model

$$\frac{P_r}{P_t} = K \left(\frac{d_0}{d}\right)^{\gamma} \qquad P_r = P_t K d_0^{\gamma} \propto \frac{1}{d^{\gamma}}$$

- *K* is a unitless constant which depends on the antenna characteristics and the average channel attenuation
- d_0 is a reference distance for the antenna farfield
 - Typically 1-10 m indoors and 10-100 m outdoors.
- γ is the **path loss exponent**.
 - 2 in free-space model
 - 4 in two-ray model [Goldsmith, 2005, eq. 2.17]

Captures the essence of signal propagation without resorting to complicated path loss models, which are only approximations to the real channel anyway!

Environment	γ range
Urban macrocells	3.7-6.5
Urban microcells	2.7-3.5
Office Building (same floor)	1.6-3.5
Office Building (multiple floors)	2-6
Store	1.8-2.2
Factory	1.6-3.3
Home	3

[Goldsmith, 2005, Table 2.2]

SIR (S/I): Definition/Calculation

- $\longrightarrow K = \#$ co-channel interfering cells
- The **signal-to-interference ratio** (S/I or SIR) for a mobile receiver which monitors a forward channel can be expressed as

$$\overline{SIR} = \frac{P_r}{P_{\text{interference}}} = \frac{P_r}{\sum_{i=1}^{K} P_{\text{of the } i^{th} \text{ interference}}}$$

- P_r = the desired signal **power** from the desired base station
- P_i = the interference **power** caused by the *i*th interfering cochannel cell base station.
- Often called the carrier-to-interference ratio: CIR.

SIR Threshold

- The SIR should be greater than a specified threshold for proper signal operation.
- In the 1G **AMPS** system, designed for **voice** calls, the threshold for acceptable voice quality is SIR equal to 18 dB.
- For the 2G digital AMPS system (D-AMPS or IS-54/136), a threshold of 14 dB is deemed suitable.
- For the **GSM** system, a range of **7–12 dB**, depending on the study done, is suggested as the appropriate threshold.
- The probability of error in a digital system depends on the choice of this threshold as well.

SIR: N = 3

Approx.

(Ignore co-channel cells that are too far away)


- Consider only first tier.

Worse-case distance
$$\frac{\sqrt{3}R}{\sqrt{7}R} = \frac{\sqrt{3}R}{\sqrt{3}R}$$

$$\frac{\sqrt{3}R}{\sqrt{2}} = \frac{\sqrt{3}R}{\sqrt{2}} = \frac{1}{\sqrt{2}R} = \frac{1}{$$

If N = 19, will the SIR be better or worse?

Approximation




- Consider only first tier.
- Worse-case distance

$$SIR \approx \frac{1}{\sum_{i} \left(\frac{D_{i}}{R}\right)^{-\gamma}}$$

• Use the same D for D_i

Approximation



- Consider only first tier.
- Worse-case distance

$$SIR \approx \frac{1}{\sum_{i} \left(\frac{D_{i}}{R}\right)^{-\gamma}}$$


• Use the same D for D_i

SIR
$$\approx \frac{1}{\sum_{i} \left(\frac{D}{R}\right)^{-\gamma}} \approx \frac{1}{K\left(\frac{D}{R}\right)^{-\gamma}} = \frac{1}{K} \left(\frac{D}{R}\right)^{\gamma}$$

Notice that D/R is an important quantity!

Center-to-center distance (D)

$$D = \sqrt{\left(i\sqrt{3}R\right)^2 + \left(j\sqrt{3}R\right)^2 - 2\left(i\sqrt{3}R\right)\left(j\sqrt{3}R\right)\cos\left(120^\circ\right)}$$
$$= R\sqrt{3\left(i^2 + j^2 + ij\right)} = R\sqrt{3N}$$



This distance, *D*, is called **reuse distance**.

Co-channel reuse ratio

$$Q = \frac{D}{R} = \sqrt{3N}.$$


Q and N

Co-channel reuse ratio

$$Q = \frac{D}{R} = \sqrt{3N}.$$

	Cluster Size (N)	Co-channel Reuse Ratio (<i>Q</i>)
i = 1, j = 1	3	3
i = 1, j = 2	7	4.58
i = 0, j = 3	9	5.20
i = 2, j = 2	12	6

Approximation: Crude formula



SIR =
$$\frac{P_r}{P_{\text{interference}}} = \frac{P_r}{\sum_{i=1}^{K} P_{\text{of the } i^{th} \text{ interferer}}}$$


 $\approx \frac{1}{\sum_{i} \left(\frac{D_i}{R}\right)^{-\gamma}} \approx \frac{1}{K \left(\frac{D}{R}\right)^{-\gamma}} = \frac{1}{K} \left(\frac{D}{R}\right)^{\gamma}$

$$= \frac{1}{K} \left(\sqrt{3N}\right)^{\gamma}$$

As the cell cluster size (N) increases, the spacing (D) between interfering cells increases, reducing the interference.

Summary: Quantity vs Quality

S = total # available duplex radio channels for the system



SIR: N = 7

Better approximation...

